

---

Subject: Re: domestic violence weights at psu level  
Posted by [Bridgette-DHS](#) on Mon, 20 Mar 2023 19:30:04 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Following is a response from Senior DHS staff member, Tom Pullum:

We recommend using `svyset` and `svy` for your final analyses, at least. Your `svyset` command would look like this: `"svyset v001 [pweight=d005], strata(v023) singleunit(centered)"`. If any of your variables come from the DV module, `d005` is preferable to `v005`, because it is adjusted for nonresponse to the module. The `svy` adjustments, and the use of `d005` in place of `v005`, will not have a huge effect on your results, but they are strongly recommended.

---